

# Gespage eTerminal Kyocera

Manual

# Table of contents

1.	Introd	uction	5
	1.1 C	ompatibility	6
2.	Config	uration	7
	2.1 C	onfiguration on the MFP	7
	2.1.1	1.1 Installation of Gespage applicatin	 
	2.1.1	1.2 Activation of Gespage default application	
	2.1.2	Configuration Gespage application on the MFP	
	2.1.3	Access to the administrator setting on the MFP	
	2.1.4	Configuring advanced scans	
:	2.2 G	espage configuration	11
	2.2.1	General	
	2.2.1	I.1 Global parameters	
	2.2.1	1.2 Network flows	
	2.2.2	Configuration of an eTerminal	
	2.2.2	2.1 eTerminal general parameters	
	2.2.2	2.2 eTerminal advanced parameters	
	2.2.3	eTerminal general configuration	
	2.2.3	3.1 General parameters	
	2.2.3	3.2 Advanced parameters	
3.	Use		19
:	3.1 E	xamples of user menus	19
	3.1.1	User login	
	3.1.2	Select a billing code	
	3.1.3	Gespage home page	
	3.1.4	Screen of print release	22
	3.1.5	Gespage scan screen	

# 1. Introduction

Kyocera eTerminal is a Gespage software module dedicated to Kyocera MFPs. This module uses the integrated touch screen of the MFP.

This module enables an authentication at the MFP to provide the following functions:

- Print2me secured print with user authentication (by login / password, PIN code, RFID card) and user-friendly selection of the documents to print.
- Modification of the job properties (print forcing in B&W, in Duplex or change of the number of copies).
- Scan to me by email or to a home directory.
- Payment and retrieval of prints (including USB), copies and scans performed to Gespage server.
- Access rights to copy, print (B&W, color) and scan functions.
- Management and configuration of the terminal from a user-friendly Web interface.

	Welcome
	*Gespag
Username	
Password	
Approve	

# **1.1 Compatibility**

Gespage eTerminal is compatible with all Kyocera MFPs featuring the HyPAS platform.

**ATTENTION!** Some Kyocera HyPAS MFPs require an additional external memory to launch HyPAS applications (ECOSYS or FS models).

For detailed information about supported models, it is recommended to consult **CartadisDB** tool.

The card readers that can be connected are Cartadis card readers such as TCM3 or TCM4.

**ATTENTION!** The use of a reader requires the addition of an OEM license Kyocera for RFID reader.



# 2. Configuration

# 2.1 Configuration on the MFP

Before configuring the MFP, the printer matching your MFP must first be configured on your Gespage server.

Gespage application must then be installed on your Kyocera MFP.

#### 2.1.1.1 Installation of Gespage applicatin

Gespage application is available in the installation directory of your Gespage server under *GespageCore\server\resources\medias\kyocera\GespageKyocera.pkg.* 

The application can be installed in 2 ways on your MFP.

- USB key
  - Copy the GespageKyocera.pkg file to a FAT32 formatted USB key.
  - At the MFP, move to the *System* menu and select the *Application* menu. You have to log in as administrator.
  - Press the Add button.
  - Insert the USB key into the copier (rather on the display panel) and wait for *Gespage* display in the list.
  - Select *Gespage* application, click *Install* and validate.
  - Click *Remove memory* to remove your USB key safely.
  - Choose *Click* to exit the menu.
  - Select Gespage application, click Activate and validate.
  - Wait until Gespage screen appears on the copier.
- <u>With Kyocera NetViewer copier tool</u>

Kyocera NetViewer is a tool management of KYOCERA MFPs dedicated to the network installation of Gespage application.

- Launch Kyocera Net Viewer application.
- Add your printer.
- Right-click on your printer, select *Modify* and *Application*.
- From the new screen, click *Install a new* and select the *GespageKyocera.pkg* file and validate.
- Once *Gespage* application appears, right-click and select *Activate*.
- Select Activate without licence key and validate.
- Wait until Gespage screen appears on the copier.

#### 2.1.1.2 Activation of Gespage default application

After installation, Gespage application must be enabled by default from the MFP administration menu.

lome	Сору	Send	Status
Custom Box	Job Box	Removable Memory	Program
lome Accessibility)	Accessibility Copy	Accessibility Send	

To that end, move to the MFP administration menu with the Z code (see §2.1.3), then select *Gespage* from the menu *System/ Common settings/ Default screen*.

ATTENTION! This parameter must be set again after every *Gespage* application reinstallation.

### 2.1.2 Configuration Gespage application on the MFP

At first start, Gespage application displays the network settings configuration menu of communication with Gespage server.

The application will be operational only after Gespage server address setting.

Settings	
	•
	Gespage
	1 5
Set Gespage's parameters	
Server address:	
10.0.100.22	
Server's port:	
0	
SSL activated:	
Device access Apply	
©GespageKyocera 1.3.0	

#### Server's IP

IP address or hostname of Gespage server.

#### Server's port

Communication port with the server (0 = use of Gespage standard ports). Please keep this parameter set to 0 unless specific configuration.

#### SSL Activated

SSL enabled in the communication with the server.

This parameter should remain active.

Note: This configuration menu may also be displayed in a browser with the following address: <u>http://Adresse\_MFP:8080/GespageKyocera/jsp/wide/setup.jsp</u>

### 2.1.3 Access to the administrator setting on the MFP

After Gespage application installation, the MFP administration menu is accessible from the Gespage administration menu.

The administration menu is displayed from the MFP by entering the Z code on the Gespage login screen (pressing the 4 corners of the screen in the order shown below). Then, enter the login and administrator password of the MFP.

	Welcome	
Login Username Password Copprove	2	(Gespage)
©.	GespageKyocera 1.3.0	

Gespage parameters are accessible.

	Setting	S	
			<b>Gespage</b>
	Set Gespage's par	ameters	
	Server address: 10.0.100.22		
	Server's port: 0		
	SSL activated:		
De	evice access	Apply	
			-
	@CoopersKuesers	120	
	Gespagekyocera	1.3.0	

The MFP administration menu is accessible by selecting *Device access* menu.

# 2.1.4 Configuring advanced scans

Installation of the "Gespage Mobile" licence is required to use the advanced scans feature. It is included in the standard licence and can be requested from your Gespage contact

For more information on configuring Gespage advanced scans, you can refer to § "12.3.3 Using scan profiles" of the Gespage manual.

# 2.2 Gespage configuration

## 2.2.1 General

#### 2.2.1.1 Global parameters

Make sure that the required licences are available. From *Server/Support/Licence*, information about your Gespage Server and the licenses bought are available. An eTerminal can be installed only if you have a Kyocera eTerminal license available or if your server is in demo mode.

View licence							
icense							
Signature YEGYKQ	ME						
Mode Active (under maintenance)							
Maintenance end date 29 févr. 2020							
Qty of printers 50							
Qty of physical printers 27							
Torminale	Mode	Details	Date	Number of devices			
Terrinidas			29 févr. 2020	50			
eTerminal Kyocera	Active (under maintenance)	License registration Register your license key					

After purchase, a new licence can be registered just by uploading and validating from this menu.

#### 2.2.1.2 Network flows

Kyocera eTerminal communicates with Gespage service on the TCP ports 7180/7181.

Scan to email or Home directory by FTP require the opening of the TCP port 7121 (default) between the copier and the server. The embedded FTP server by Gespage operates in active mode for transporting data (the server port number opening the connection to the client is random).

# 2.2.2 Configuration of an eTerminal

When the application is installed and set on the MFP, Kyocera eTerminal will register automatically on Gespage server. It is accessible by moving to *Printers/Terminals/List of Terminals*. Your eTerminals will be in *Kyocera* tab.

If the print queue of your MFP was created prior to the installation of the application, your print queue will be automatically associated with your eTerminal in Gespage after its registration.

General parameters Advanced	parameters
Kyocera	
Name	kyocera_LHD3800331
Serial number	LHD3800331
MFP address	10.0.0.23
Comments	
Reader profile	- •
Public mode	Disabled
	O Enabled
Drine ink and and	Manually
Print Job release	O Automatically
Manual releasing condition	O All jobs are automatically released after user login
Manual releasing condition	Jobs are released after a keyboard selection
Enable Operator release	
Allow to change job properties	(depending on printer driver or printer version)
Change number of Conjes	

#### 2.2.2.1 eTerminal general parameters

By clicking on your eTerminal, its features may be changed.

#### <u>Name</u>

The eTerminal name must be filled in. The name is free but 2 identical names cannot be entered.

#### <u>Serial number</u>

Serial number of the MFP. This number is automatically filled in at MFP automatic recording.

**ATTENTION!** The identifier of your MFP is its serial number. If you replace your MFP, a new eTerminal corresponding to the new serial number will register.

#### MFP address

Address (IP or hostname) of the MFP on which the eTerminal is installed.

#### <u>Comments</u>

Comment of the eTerminal in Gespage. Comments are optional.

#### Reader profile

Name of a reader profile associated with the card reader (see Gespage manual).

The reader profile is an advanced parameter useful when non-standard card readers have to be connected or when the numbers of the cards stored on Gespage do not match the standard format.

#### <u>Public mode</u>

This parameter enables a 'Public' tab to be activated on the login screen of the eTerminal for accessing certain MFP functionalities in free access.

#### 1. Disabled

Disables the public mode.

#### 2. Enabled

#### Enables the public mode.

**ATTENTION:** In addition to this parameter enabling, a Gespage user account must be defined for the definition of functionalities authorized to the public mode (**public** user account to define by default, configurable via the *conf\_public\_username* advanced parameter).

#### Print job release

Indicates whether printings sent to the MFP are locked as long as the user is not identified.

#### 1. Manually (fonction Print2me)

The user must always authenticate to release his documents. This is the configuration to choose for getting a secured printing.

#### 2. Automatically

The documents are printed as soon as they are received if the user's credit is sufficient, they are nevertheless accounted.

#### Manual releasing condition

This parameter indicates whether all printings are automatically released or the user can select the ones that he wishes to release.

#### 1. All jobs are automatically released after a user login

Once the user is identified, all his printings are released from the queue.

#### 2. Jobs are released after a keyboard selection

Once the user is identified, a scrolling list shows to the user all his printings in the queue and the opportunity of their release is proposed to him.

#### Enable Operator release

This parameter enables operator printing at the MFP.

Operator printing enables documents of other users to be released for certain authorized users (executive secretary, reprographic service) see the Gespage manual.

To set the operator accesses at user account level, please refer to the Gespage manual.

#### Allow to change job properties

This option gives access to tabs in the print release screen to allow the user to change some print options directly on the MFP screen. According to the configuration selected, he can modify the number of copies of his print, force duplex and force black and white

**ATTENTION:** Only a simplex can be forced in duplex and a colour printing in black and white. The reverse is not possible. Moreover, these features are only available with a PCL or PS Driver.

#### General parameters Advanced parameters Name Value admin\_copy\_access false auto\_logout 180 conf\_public\_username public debug mode false filter\_ip\_enable false polling-timeout 60 30 screen timeout screen\_to\_display application 💼 Delete

#### 2.2.2.2 eTerminal advanced parameters

Some advanced parameters are configurable from the Advanced parameters tab of the eTerminal.

- activate\_log=false
   This parameter enables the eTerminal logs to be recovered to Gespage server. It is to enable on request of Gespage support.
- admin\_copy\_access=false This parameter defines whether copies are allowed when an administrator is logged in the administration menu.
- auto\_logout=180
   This parameter defines the disconnection timeout of the eTerminal (in seconds).
- conf\_public\_username=public

This parameter defines the user account name used for accounting and the rights of the account of public access.

- debug\_mode=false This parameter enables the logs of the eTerminal at debug level.
- polling-timeout=180
  - This parameter defines the refresh period of the eTerminal configuration (in seconds).
- screen\_timeout=30

This parameter defines the display time of the information screens (in seconds).

• screen to diplay=default

By default, after a login, if the user has pending prints, they are displayed, otherwise the screen of copies is displayed. This parameter enables the home screen to be changed after login. The values available are default (Gespage), copy (screen of copies), send (screen of scans), home\_menu (home screen).

# 2.2.3 eTerminal general configuration

In the screen of Kyocera eTerminals general configuration, set up the parameters to be applied to all Kyocera eTerminals on the site.

These parameters include the type of login allowed as well as the process for card association.

#### 2.2.3.1 General parameters

General parameters Advanced parameters	
Allow to self-register	۵
Authentication method used with Cartadis terminal	
For a keyboard login	Input of the print code
For a card login	Card without password 💙
	Card and keyboard
Allowed logins	O Card only
	O Keyboard only
	Done by the users
Association card ID to user	O Done by the administrator
Allow alternative keyboard login (Input of account and password)	
User session parameters	
View the Gespage home page	
Advanced scans settings	
Resolution	300 🗸
Color	
Single	

#### The parameters are:

#### Allow to self-register

This parameter enables the automatic self-registration of the e Terminals in Gespage after the installation of Gespage application on the MFPs.

#### Authentication method used with Cartadis terminal

#### For a keyboard login

This parameter is used to select the user login mode on the keyboard.

The user will only enter his Gespage login.

Input of Gespage account only: Input of account and password: Input of the print code:

The user will enter his Gespage login and his password. The user will enter his print code.

#### For a card login

- 1. Card without password
- 2. Card + password
- 3. Card + PIN.

#### Allowed login

This parameter is used to select the peripheral for login.

#### 1. Card and keyboard

The user login can be done by card or keyboard. If no card reader is connected, keyboard login is the only option.

#### 2. Card only

The keyboard will be disabled. The MFP will only use the card reader peripheral to log the user.

#### 3. Keyboard only

The card reader peripheral will be disabled. Keyboard login is the only option.

For card login, the Cartadis TCM3 contactless card reader is recommended (Mifare 13.63 MHz or 125 kHz cards).

**NOTE:** TCM3 can be directly connected in USB on the MFP.



#### Association card ID to user

At the first user's card use and if the card number is not known by Gespage, a method of association of the card must be defined. It enables the number of the user's card to be stored in Gespage account. This association only applies at the first card insertion.

#### 1. Done by the users

When a user will use an unknown card, he will have the possibility of identifying on the keyboard at the login screen. The card self-association will be required only once during the card life time

#### 2. Done by the administrator

All card numbers of users have to first be configured in Gespage. The initialization can be carried out by the administrator or by the LDAP synchronization mechanism.

**NOTE:** The interface language of the eTerminal will be the language set on the MFP. A MFP reboot may be required after modification of the language on the MFP.

#### <u>Allow alternative keyboard login</u> (Input of account and password)

This parameter enables two keyboard login modes to be activated on the MFP at the same time (login enabled by user / password in addition to the print code).

#### User session parameters

#### View the Gespage home page

This parameter enables the Gespage homepage to be displayed for using the Gespage scan function. If Gespage home page is disabled, the following parameter is available:

*Don't show pending jobs after login* if *job list is empty*: skips over the Gespage screen of pending prints during login if there is no pending print.

#### Advanced scans settings

*<u>Resolution</u>*: sets the default value for the scan resolution. The possible values are 150, 200, 300, 400 or 600 (dpi).

<u>*Color*</u>: sets the default value for using color.

*Single*: sets whether the scan is duplex or not by default.

#### 2.2.3.2 Advanced parameters

You can set the custom value of the advanced parameters that you wish to see automatically assigned to all new eTerminals.

To that end, the advanced parameter with its value must be added in the list of advanced parameters of the general configuration.

General parameters Advanced parameters	
Name	Value
The list is empty.	
💼 Delete	
Add new parameter	
Name	

# **3.** Use

# 3.1 Examples of user menus

## 3.1.1 User login

The user must authenticate to access to the MFP services. After authentication, the user has a default access to his pending prints, if he wishes to switch to another service, he just needs to click the *Home* button.

Disconnection is made as follows:

- via the *Disconnection* button displayed on the MFP screen.
- via the Authentication/Logout key on the MFP.

|--|

	Welcome
LOGIN Username Password	<b>Cespage</b>
© Ges	spageKyocera 1.3.0

Home screen with print code authentication

	Welcome		
Print code	Cespage		
© GespageKyocera 1.3.0			

### Home screen with card authentication

Welcome	
	•
Swipe your card	Gespage
<b>2 »</b>	
© GespageKyocera 1.3.0	

Gespage eTerminal Kyocera Manual – June 2022

Home screen with public access

A public access may be enabled for accessing certain functions of the peripheral without user login. It is made by using the *Public* button.

	Welcome	Public
Please choo	ose your authenticatio	<b>Gespage</b> In mode
Username and password		<b>》</b>
Print code		
	© GespageKyocera 1.3.0	

# 3.1.2 Select a billing code

If *Billing code* is enabled, the user will charge his prints and his expenses of copies and scan to a billing code.

	Gespage	
Fast selection :	Economy	
Financial	Financial	
Filter with the following	History	
characters :	Mathematics	
	Physical education	
Search Reset		

The list of billing codes allowed for the user is displayed by pressing the button

### 3.1.3 Gespage home page

After user's login, this page is displayed to facilitate the customer journey. **NOTE**: This menu must be enabled in the general configuration of Kyocera terminals.

ŵ	Home	<b></b>
		<b>Edouard Saintilus</b>
PRINT	SCAN	COPY
	Gespage	

The following options are available to the user:

- "PRINT" button: redirect to the Gespage print release page.
- "SCAN" button: redirect to the Gespage scan menu.
- "COPY" button: redirect to the copy menu of the MFP.

## 3.1.4 Screen of print release

The screen for print release enables pending prints to be selected for printing, deleting or modifying.

The screen for print release is displayed after login and the Gespage shortcut in the home menu.



Print refreshing	Modification of the billing code	Job selected
	$\backslash$	
Per	nding jobs	
🕑 🗾 Selected: 5 / 5	115.00 €	Edouard Saintilus
FR_Gespage_eTer_120221_111623099 1h ago , 25 Pages , Simplex, Black & White, Color	42.00 t	Credit: 379.50 €
Passation Kyoce_120221_111528291 1h ago , 31 Pages , Simplex, Black & White, Color	61.00 €	ctivity: Economie
CR_2021-02-11_G_120221_111510098 1h ago , 2 Pages , Simplex, Color	4.00 €	Job modification
Installation d'_120221_111502801 1h ago , 2 Pages , Simplex, Color	4.00€	Change to duplex
Trame salarié p_120221_111451368	4.00€	Change to black and white
	C	Change number of copies
		A Environmental impact
Detail of the environment	vironmental ints selected	Printing of the
To select / deselect pending	Deletion o	documents selected
prints, click the line wished	prints selec	cted

The environmental impact informs the user about the impact of his prints on the environment.

The cost of printing automatically appears at the end of each print line. The total cost is available at the top of the screen

The page of pending prints may contain a maximum of five prints, beyond a pagination will be applied.

Job modification Forcing to duplex Change to duplex Forcing to Change to black and white Black&White Change the number of copies Change number of copies

#### 3.1.5 Gespage scan screen

Forcing keys enable the printing to be changed:

The Gespage scan menu is accessible from the "ADVANCED SCAN" menu of the home page. ATTENTION! This menu is not compatible with device before XX51 series.



It opens a window for modifying the scan options

It performs the scan with the default parameter

•			Scan s	ettings		
	Original document			Scanned document		
Size	Orientation	Duplex	Mode	Types	Resolution	Color
<b>A</b> 4	0	Ð		PDF	200	
				TIFF	300	
				JPEG	400	
					600	
						$\geq$

The scan links displayed in this menu depend on the scan parameters set in Gespage and the user's access rights.

**NOTE:** Several advanced scans cannot be selected simultaneously. Each scan must be performed separately.